Package 'indirect'

July 22, 2025

Type Package

Title Elicitation of Independent Conditional Means Priors for
Generalised Linear Models

Version 0.2.1

Date 2022-02-09

Author Geoffrey R. Hosack

Maintainer Geoff Hosack <geoff.hosack@csiro.au>

Description Functions are provided to facilitate prior elicitation for Bayesian generalised linear models using independent conditional means priors. The package supports the elicitation of multivariate normal priors for generalised linear models. The approach can be applied to indirect elicitation for a generalised linear model that is linear in the parameters. The package is designed such that the facilitator executes functions within the R console during the elicitation session to provide graphical and numerical feedback at each design point. Various methodologies for eliciting fractiles (equivalently, percentiles or quantiles) are supported, including versions of the approach of Hosack et al. (2017) <doi:10.1016/j.ress.2017.06.011>. For example, experts may be asked to provide central credible intervals that correspond to a certain probability. Or experts may be allowed to vary the probability allocated to the central credible interval for each design point. Additionally, a median may or may not be elicited.

License GPL-3

Depends R (>= 3.1.0)

Imports MASS, gplots

Suggests tools, utils

RoxygenNote 7.1.2

NeedsCompilation no

Repository CRAN

Date/Publication 2022-02-09 05:30:02 UTC

Contents

---

checkX   *Helper function that checks for sensible covariate matrix.*

Description

Helper function that checks for sensible covariate matrix.

Usage

```
checkX(X)
```

Arguments

X   numeric matrix of covariates, n design points by p covariates, for a given model
                     and design points.

Value

throws an error if not full rank.

CNdiag   *Function to check condition number diagnostic.*

Description

This function calculates the condition number of the rescaled nxp design matrix X such that each
column has unit length.

Usage

```
CNdiag(X)
```

Arguments

    X   Design matrix

Value

    a scalar giving the condition number of the rescaled design matrix

Examples

```
X <- matrix(rnorm(16), nrow = 4)
CNdiag(X)
```

---

    designLink   *Create list with information for the elicitation session*

Description

This builds the structure that will store elicited data. The linear predictor has a normal prior $g(\theta) \ N(m, V)$, θ is the elicitation target. Link functions $g(.)$: `logit`, `log`, `cloglog`, `identity`.

Usage

```
designLink(
  design,
  link = "identity",
  target = "Target",
  CI.prob = 1/2,
  expertID = "Expert",
  facilitator = "Facilitator",
  rapporteur = "none",
  intro.comments = "This is a record of the elicitation session.",
  fit.method = "KL"
)
```

Arguments

design	a dataframe with covariate values that will be displayed to the expert(s) during the elicitation session.
link	character `logit`, `log`, `cloglog`, `identity`
target	character, name of target parameter of elicitation exercise
CI.prob	numeric, a fraction between 0 and 1 that defines probability attributed to central credible interval. For example, 1/2 for a central credible interval of probability 0.5, or 1/3 for a central credible interval of probablity 0.333... The default is probability 1/2.
expertID	character, identifier for expert or group of experts
facilitator	character, facilitator identifier

rapporteur	character, rapporteur identifier. Default "none".
intro.comments	character, text with any prefacing comments. This may include, for example, the definition of the target parameter for the elictation session. Beware of non-ASCII text and special characters, which may affect the ability to save the elicitation record with function saveRecord or create a summary report with function makeSweave if called by the function makeSweave may affect ability to render by means of Sweave or knitr etc.
fit.method	character, method used to fit conditional means prior: KL (default), moment, SS (see vignette and mV for more information on these options)

Details

Assumption: at least two fractiles selected from the median, upper and lower bounds of hte central credible interval of probability CI.prob will be elicited at each design point. The probabilities assigned to the central credible intervals can vary across design points. The argument CI.prob can later be adjusted by design point during the elicitation exercise, see function elicitPt. In the first instance, it is set to a global value specified by CI.prob in function designLink with default value 0.5.

Value

list of design with entries: theta, a $nx4$ matrix with columns that give lower, median and upper quantiles followed by CI.prob and n equal to the number of design points (scenarios); link, the link function used; target; expert facilitator; rapporteur; date; intro.comments; fit.method.

Examples

```
X <- matrix(c(1, 1, 0, 1), nrow = 2) # design
Z <- designLink(design = X, link = "logit", target = "target",
 CI.prob = 1/2, expertID = "Expert", facilitator = "facilitator")
```

---

dGompertzNorm	*density for Gompertz transformed univariate Gaussian*

Description

density for Gompertz transformed univariate Gaussian

Usage

```
dGompertzNorm(x, mu, sigma)
```

Arguments

x	numeric real
mu	numeric real
sigma	numeric real positive

Value

tranformed density on support (0, 1)

Examples

```
mu <- -1
sigma <- 1
z <- rnorm(10000, mu, sigma)
hist(1 - exp(-exp(z)), freq = FALSE)
curve(dGompertzNorm(x, mu = mu, sigma = sigma), col = 'red', add = TRUE, from = 0.01, to = 0.99)
integrate(function(x) dGompertzNorm(x, mu = mu, sigma = sigma), lower = 0, upper = 1) # equals 1
```

---

dLogitNorm   *density for logit transformed univariate Gaussian*

Description

density for logit transformed univariate Gaussian

Usage

```
dLogitNorm(x, mu, sigma)
```

Arguments

x	numeric real
mu	numeric real
sigma	numeric real positive

Value

tranformed density on support (0, 1)

Examples

```
mu <- -1
sigma <- 1
z <- rnorm(10000, mu, sigma)
hist(exp(z)/(1 + exp(z)), freq = FALSE)
curve(dLogitNorm(x, mu = mu, sigma = sigma), col = 'red', add = TRUE, from = 0.01, to = 0.99)
integrate(function(x) dLogitNorm(x, mu = mu, sigma = sigma), lower = 0, upper = 1) # equals 1
```

elicitPt	*Function to create or update elicitation at a given design point.*

Description

Function to create or update elicitation at a given design point.

Usage

```
elicitPt(
  Z,
  design.pt = NULL,
  lower.CI.bound = NA,
  median = NA,
  upper.CI.bound = NA,
  CI.prob = NULL,
  comment = " "
)
```

Arguments

Z	list of `design` with entries: `theta`, a $nx4$ matrix with columns that give lower, median and upper quantiles of the central credible interval followed by the probability `CI.prob` allocated to the interval; `link`, the link function used; and `target`. This list object is created by [designLink](#)
design.pt	single integer that denotes design point of interest
lower.CI.bound	scalar that gives the lower bound of the central credible interval, default NA.
median	scalar value, default NA
upper.CI.bound	scalar that gives the upper bound of the central credible interval, default NA.
CI.prob	numeric, a fraction between 0 and 1 that defines probability attributed to central credible interval. For example, 1/2 for quartiles or 1/3 for tertiles. Default NULL uses the initial `CI.prob` as defined by [designLink](#).
comment	character, ASCII text providing contributed commentary associated with elicitation design point. It is recommended to avoid special characters such as quotation marks etc.

Value

Z, a list of `design` with entries: `theta`, a $nx4$ matrix with columns that give lower, median and upper quantiles followed by `CI.prob` with updated entries for row specified by argument `design.pt`; `link`, the link function used; and `target`.

Examples

```
X <- matrix(c(1, 1, 0, 1), nrow = 2) # design
Z <- designLink(design = X)
Z <- elicitPt(Z, design.pt = 1,
  lower.CI.bound = -1,
  median = 0,
  upper.CI.bound = 1,
  comment = "A completed elicitation scenario.")
```

---

indirect	*indirect: A package for assisting indirect elicitation of priors for generalised linear models.*

Description

The `indirect` package provides three categories of functions: elicitation functions, fitting functions and visualisation functions.

Elicitation functions

These are the functions that are used to record expert opinion. This is where edits will be made and so on. The key function is designLink, which defines a list object that contains information about the design and elicitation. The elicitations are recorded and updated via function elicitPt.

Fitting functions

These are generally helper functions except for the function muSigma that is used for estimating the mean vector and covariance matrix of the unknown coefficients for the multivariate normal prior. Helper functions include mV for the elicited moments of conditional means priors.

Visualisation functions

These are functions for visualisation. The core function is plotDesignPoint.

References

Hosack, G. R., Hayes, K. R., & Barry, S. C. (2017). Prior elicitation for Bayesian generalised linear models with application to risk control option assessment. Reliability Engineering and System Safety, 167:351-361. doi:10.1016/j.ress.2017.06.011

---

makeSweave | *Function to create summary document from a saved elicitation record.*

Description

Creates a Sweave file that can be used to generate a pdf document of the summary report.

Usage

```
makeSweave(
  filename.rds = "",
  reportname = "",
  title = "Elicitation record",
  contact.details = "none",
  fitted.fractiles = TRUE,
  cumul.prob.bounds = c(0.05, 0.95)
)
```

Arguments

filename.rds   character, filename of the record saved as an RDS object, see ?saveRDS.

reportname   character, filename without extension to be used for the generated Sweave (.Rnw)
                file. The Sweave file supports the creation of report (.pdf) documentation and
                accompanying files such as the .tex file generated by using [Sweave](#) followed
                by tools::texi2pdf().

title   character, a title for the report

contact.details

                character, an email address or other mechanism by which the expert may contact
                the facilitator or rapporteur

fitted.fractiles

                logical or numeric vector. A logical value of FALSE will not plot any fitted
                fractiles from the fitted subjective probability distribution. A logical value of
                TRUE will plot the fitted fractiles that correspond to the final iteration of the raw
                elicited fractiles. Alternatively, a numeric vector can specify arbitrary fractiles
                for plotting from the fitted distribution, e.g., c(1/10, 1/4, 1/2,3/4, 9/10)

cumul.prob.bounds

                numeric vector that specifies the upper and lower plot bounds determined by
                this credible interval. The default is the 0.90 central credible interval, c(0.05,
                0.95)

Examples

```
## Not run:
X <- matrix(c(1, 1, 0, 1), nrow = 2) # design
Z <- designLink(design = X)
Z <- elicitPt(Z, design.pt = 1,
```

```
    lower.CI.bound = -1,
    median = 0,
    upper.CI.bound = 1,
    comment = "A completed elicitation scenario.")
tmp.rds <- tempfile(pattern = "record", fileext =".rds")
saveRecord(Z, file = tmp.rds)
tmpReport <- tempfile(pattern = "report")
makeSweave(filename.rds = tmp.rds, reportname = tmpReport)
setwd(tempdir())
utils::Sweave(paste0(tmpReport, ".Rnw"))
tools::texi2pdf(paste0(tmpReport, ".tex"))

## End(Not run)
```

---

muSigma   *Function to estimate mean and covariance for unknown parameters β.*

Description

Function to estimate mean and covariance for unknown parameters β.

Usage

```
muSigma(Z, X = NULL, fit.method = "KL", wls.method = "default")
```

Arguments

Z	list of design points and link function that is an output of function designLink
X	model matrix for model formula and design points. The covariates must correspond to the description of design points in Z, but can be transformed etc. If NULL then X will be coerced by applying as.matrix() to Z$design. The matrix X should be full rank when subsetted to the elicited design points. If a column of X has the name offset then this column is treated as an offset during estimation
fit.method	character, moment, KL. See mV. Default is KL.
wls.method	character giving the numerical solution method: QR, using the QR decomposition, SVD, using the singular value decomposition, or option default that uses solve()

Value

list of mu, numeric vector of location parameters for the normal prior; Sigma, the covariance matrix; and log.like, a scalar

Examples

```
X <- matrix(c(1, 1, 0, 1), nrow = 2) # design
Z <- designLink(design = X)
Z <- elicitPt(Z, design.pt = 1,
  lower.CI.bound = -1,
  median = 0,
  upper.CI.bound = 1,
  comment = "The first completed elicitation scenario.")
Z <- elicitPt(Z, design.pt = 2,
  lower.CI.bound = -2,
  median = 1,
  upper.CI.bound = 2,
  comment = "The second completed elicitation scenario.")
prior <- muSigma(Z, X, fit.method = "KL")
prior$mu
prior$Sigma
```

---

mV   *Helper function that translates elicited quantiles of target into inde-*
                            pendent conditional means normal prior for a defined inverse link
                            function.

Description

The default for `fit.method` is option `KL`. This option uses an objective function that minimises a discretised directed divergence from a cumulative distribution implied by raw elicited fractiles to a normal conditional mean prior for the linear predictor. An alterative method `moment` assigns the location parameter of the normal conditional mean prior to the elicited median on the linear predictor scale. The variance parameter is estimated as $V = ((g(f_u) - g(f_l)/(qnorm(u) - qnorm(l)))^2$, where l is the probability associated with the fractile f_l that defines the lower bound for the central credible interval and u is the probability associated with the fractile f_u that defines the upper bound for the central credible interval. This is also used to initialise the optimisation for the `KL` method. Another optimsation method that minimises the sum of squares is also available as method `SS`. See the vignette for more details on the choice of objective function for `KL` and `SS`.

Usage

```
mV(Z, fit.method = "KL")
```

Arguments

Z	list object that contains matrix `theta` of elicitations and character `link`, see [plotDesignPoint](#)
fit.method	character, `moment`, `KL`, `SS`. Default is `KL`.

Value

A list with vector of means `m` and diagonal covariance matrix `V`.

---

pdist   *Helper function that gives the probability distribution function for de-sign point.*

Description

Helper function that gives the probability distribution function for design point.

Usage

```
pdist(x, Z, design.pt = NULL, fit.method = "KL")
```

Arguments

x	numeric: coordinate
Z	list of design points and link function, see [designLink](#)
design.pt	integer: design point
fit.method	character: method for fit in [mV](#), default is KL

Examples

```
# design matrix: two scenarios
X <- matrix(c(1, 1, 0, 1), nrow = 2)
rownames(X) <- c("scenario1", "scenario2")
colnames(X) <- c("covariate1", "covariate2")
#' # logit link
# central credible intervals with probability = 1/2
Z <- designLink(design = X, link = "logit", CI.prob = 0.5)
#' # lower and upper quartiles and median
Z <- indirect::elicitPt(Z, design.pt = 1,
  lower.CI.bound = 0.2,
  median = 0.4,
  upper.CI.bound = 0.6,
  comment = "Completed.")
indirect::plotDesignPoint(Z, design.pt = 1,
  elicited.fractiles = TRUE, theta.bounds = c(0, 1),
  fitted.fractiles = TRUE, fitted.curve = TRUE)

# probability that target is below 0.1 and
# probability that target is below 0.9
indirect::pdist(c(0.1, 0.9), Z, design.pt = 1)
```

---

plotDesignPoint   *Plot elicited data, fitted marginals or model output*

Description

Plot elicited data, fitted marginals or model output

Usage

```
plotDesignPoint(
  Z,
  X = NULL,
  design.pt = NULL,
  elicited.fractiles = TRUE,
  fitted.fractiles = FALSE,
  fitted.curve = FALSE,
  CI.prob = NULL,
  estimated.probs = NULL,
  modelled.fractiles = FALSE,
  modelled.curve = FALSE,
  cumul.prob.bounds = c(0.05, 0.95),
  theta.bounds = NULL,
  ylim.max = NULL,
  xlog = FALSE,
  design.table = TRUE,
  n.pts = 101
)
```

Arguments

Z	list object that contains matrix theta of elicitations, character link and character target as initialised by [designLink](#) and updated by [elicitPt](#)
X	design matrix (can be NULL, unless modelled output is requested)
design.pt	single integer that denotes design point of interest
elicited.fractiles	
	logical, plot vertical lines for elicited fractiles?
fitted.fractiles	
	logical, plot vertical lines for fitted conditional mean prior fractiles for this design point? Alternatively, a numeric vector of arbitrary fractiles to be plotted from the fitted elicitation distribution. If TRUE then the fractiles corresponding to the median, upper and lower level central CI are plotted
fitted.curve	logical plot fitted conditional mean prior density for this design point?
CI.prob	numeric scalar, locally specified probability assigned to the elicited central credible interval of the current design point. Defaults to NULL in which case the global value initially assigned by [designLink](#) or as updated by [elicitPt](#) is used

estimated.probs

> numeric vector of values for which estimated probabilities are to be estimated from the fitted elicitation distribution for the target theta. Default is NULL. The result is output to the console.

modelled.fractiles

> logical, plot vertical lines for modelled fractiles from the conditional mean prior distribution fit to all design points? This option requires a design matrix X of full column rank.

modelled.curve   logical, plot modelled conditional mean prior density for the entire model? This option requires a design matrix X of full column rank.

cumul.prob.bounds

> numeric vector of length two, giving plot bounds by cumulative probability. This argument is ignored if there is not enough data to fit a parametric distribution or if theta.bounds is not NULL

theta.bounds   numeric vector giving support of response for plotting purposes (can be NULL). This will overwrite cumul.prob.bounds, if applicable

ylim.max   numeric maximum value of y-axis (can be NULL)

xlog   logical log x-axis

design.table   logical include design dataframe, elicited fractiles and modelled or fitted fractiles

n.pts   numeric giving number of point to evalate density curve (if plotted)

Value

a plot to the current device. See dev.cur() to check.

Examples

```
# design matrix: two scenarios
X <- matrix(c(1, 1, 0, 1), nrow = 2)
rownames(X) <- c("scenario1", "scenario2")
colnames(X) <- c("covariate1", "covariate2")

# logit link
# central credible intervals with probability = 1/2
Z <- designLink(design = X, link = "logit", CI.prob = 0.5)

# 1st design point
# no elicited fractiles
indirect::plotDesignPoint(Z, design.pt = 1)
# elicited median
Z <- indirect::elicitPt(Z, design.pt = 1,
  lower.CI.bound = NA,
  median = 0.4,
  upper.CI.bound = NA,
  CI.prob = NULL)
indirect::plotDesignPoint(Z, design.pt = 1,
  elicited.fractiles = TRUE, theta.bounds = c(0, 1))
# lower and upper quartiles and median
```

```
Z <- indirect::elicitPt(Z, design.pt = 1,
  lower.CI.bound = 0.2,
  median = 0.4,
  upper.CI.bound = 0.6,
  comment = "Completed.")
indirect::plotDesignPoint(Z, design.pt = 1,
  elicited.fractiles = TRUE, theta.bounds = c(0, 1),
  fitted.fractiles = TRUE, fitted.curve = TRUE)
indirect::plotDesignPoint(Z, design.pt = 1,
  elicited.fractiles = TRUE, theta.bounds = c(0, 1),
  fitted.fractiles = c(1/10, 1/4, 1/2, 3/4, 9/10),
  fitted.curve = TRUE)

# second design point
# central credible intervals with probability = 1/3
# elicit upper and lower tertiles
Z <- elicitPt(Z, design.pt = 2,
  lower.CI.bound = 0.1,
  upper.CI.bound = 0.3,
  CI.prob = 1/3,
  comment = "Switched to tertiles.")
indirect::plotDesignPoint(Z, design.pt = 2,
  elicited.fractiles = TRUE, theta.bounds = c(0, 1))
indirect::plotDesignPoint(Z, design.pt = 2,
  elicited.fractiles = TRUE, theta.bounds = c(0, 1),
  fitted.fractiles = TRUE, fitted.curve = TRUE)
indirect::plotDesignPoint(Z, design.pt = 2,
  elicited.fractiles = TRUE, theta.bounds = c(0, 1),
  fitted.fractiles = c(1/10, 1/3, 1/2, 2/3, 9/10),
  fitted.curve = TRUE)
```

---

saveRecord   *Function to save elicitation record.*

Description

Function to save elicitation record.

Usage

```
saveRecord(
  designLink.obj,
  conclusion.comments = "This concludes the elicitation record.",
  file = ""
)
```

Arguments

designLink.obj list object initally created by function [designLink](#) and subsequently updated by
                function [elicitPt](#)

conclusion.comments

        character, comments to conclude session. Beware of non-ASCII text and special characters, which may affect ability to save or generate a Sweave document by using makeSweave

file   character providing filename.

Value

an RDS file is created with filename `file`. A timestamp is added to `designLink.obj` using `Sys.time()`.

Examples

```
## Not run:
X <- matrix(c(1, 1, 0, 1), nrow = 2) # design
Z <- designLink(design = X)
tmp <- tempfile(pattern = "report", fileext =".rds")
saveRecord(Z, file = tmp)

## End(Not run)
```

Index