Package 'roseRF'

October 11, 2024

Type Package Title ROSE Rand

Title ROSE Random Forests for Robust Semiparametric Efficient Estimation

Version 0.1.0

Maintainer Elliot H. Young <ey244@cam.ac.uk>

Description ROSE (RObust Semiparametric Efficient) random forests for robust semiparametric efficient estimation in partially parametric models (containing generalised partially linear models).
 Details can be found in the paper by Young and Shah (2024) <doi:10.48550/arXiv.2410.03471>.

License GPL-3

Encoding UTF-8

RoxygenNote 7.2.3

Imports caret (>= 6.0.93), glmnet (>= 4.1.6), keras, mgcv, mlr (>= 2.19.1), ParamHelpers, ranger (>= 0.14.1), grf, rpart, stats, tuneRanger (>= 0.5), xgboost

Depends R (>= 4.2.0)

Suggests knitr, rmarkdown, testthat (>= 3.0.0)

NeedsCompilation no

Author Elliot H. Young [aut, cre], Rajen D. Shah [aut]

Repository CRAN

Date/Publication 2024-10-11 08:00:02 UTC

Contents

print.roseforest																								2
roseRF_gplm																								2
roseRF_pliv		•		•		•	•		•	•	•	•	•	•		•		•	•	•	•	•	•	6
roseRF_plm		•	•	•		•	•		•	•	•	•	•	•		•		•	•	•	•	•	•	8
summary.roseforest				•		•	•				•	•	•	•		•	•	•		•		•	•	11
unweighted_gplm .				•		•	•				•	•	•	•		•	•	•		•		•	•	11
unweighted_plm .																•								13

Index

print.roseforest *Print for a rose random forest fitted object*

Description

This is a method that prints a useful summary of aspects of a roseRF object fitted by the functions roseRF... in roseRF.

Usage

S3 method for class 'roseforest'
print(x, ...)

Arguments

х	a fitted roseRF object fitted by roseRF
	additional arguments

Value

Prints output for roseRF object

<pre>roseRF_gplm</pre>	ROSE random forest estimator for the generalised partially linear
	model

Description

Estimates the parameter of interest θ_0 in the generalised partially linear model

$$g(\mathbb{E}[Y|X,Z]) = X\theta_0 + f_0(Z),$$

for some (strictly increasing, differentiable) link function g, which can be reposed in terms of the 'nuisance functions' $(\mathbb{E}[X|Z], \mathbb{E}[g(\mathbb{E}[Y|X, Z])|Z])$ as

$$g(\mathbb{E}[Y|X,Z]) - \mathbb{E}[g(\mathbb{E}[Y|X,Z])|Z]) = (X - \mathbb{E}[X|Z])\theta_0.$$

15

Usage

```
roseRF_gplm(
 y_on_xz_formula,
 y_on_xz_learner,
 y_on_xz_pars = list(),
 Gy_on_z_formula,
 Gy_on_z_learner,
 Gy_on_z_pars = list(),
  x_formula,
  x_learner,
 x_pars = list(),
 M1_formula = x_formula,
 M1_learner = x_learner,
 M1_pars = x_pars,
 M2_formula = NA,
 M2\_learner = NA,
 M2_pars = list(),
 M3_formula = NA,
 M3_learner = NA,
 M3_pars = list(),
 M4_formula = NA,
 M4\_learner = NA,
 M4_pars = list(),
 M5_formula = NA,
 M5\_learner = NA,
 M5_pars = list(),
 link = "identity",
 data,
 K = 5,
 S = 1,
 max.depth = 10,
 num.trees = 500,
 min.node.size = max(10, ceiling(0.01 * (K - 1)/K * nrow(data))),
 replace = TRUE,
  sample.fraction = 0.8
```

Arguments

)

```
y_on_xz_formula
                  a two-sided formula object describing the model for \mathbb{E}[Y|X, Z] (regressing Y
                  on (X)).
y_on_xz_learner
                  a string specifying the regression method to fit the regression as given by y_on_xz_formula
                  (e.g. randomforest, xgboost, neuralnet, gam).
                  a list containing hyperparameters for the y_on_xz_learner chosen. Default is
y_on_xz_pars
                  an empty list, which performs hyperparameter tuning.
```

Gy_on_z_formula	1
	a two-sided formula object describing the model for $\mathbb{E}[g(\mathbb{E}[Y X,Z]) Z]$ (regressing $g(\hat{E}[Y X,Z])$ on Z).
Gy_on_z_learner	
	a string specifying the regression method to fit the regression as given by Gy_on_z_formula (e.g. randomforest, xgboost, neuralnet, gam).
Gy_on_z_pars	a list containing hyperparameters for the Gy_on_z_learner chosen. Default is an empty list, which performs hyperparameter tuning.
x_formula	a two-sided formula object describing the model for $\mathbb{E}[X Z]$.
x_learner	a string specifying the regression method to fit the regression of X on Z as given by x_formula (e.g. randomforest, xgboost, neuralnet, gam).
x_pars	a list containing hyperparameters for the x_learner chosen. Default is an empty list, which performs hyperparameter tuning.
M1_formula	a two-sided formula object for the model $\mathbb{E}[M_1(X) Z]$. Default is $M_1(X) = X$.
M1_learner	a string specifying the regression method for $\mathbb{E}[M_1(X) Z]$ estimation.
M1_pars	a list containing hyperparameters for the M1_learner chosen.
M2_formula	a two-sided formula object for the model $\mathbb{E}[M_2(X) Z]$. Default is no formula / regression (i.e. $J = 1$)
M2_learner	a string specifying the regression method for $\mathbb{E}[M_2(X) Z]$ estimation.
M2_pars	a list containing hyperparameters for the M2_learner chosen.
M3_formula	a two-sided formula object for the model $\mathbb{E}[M_3(X) Z]$. Default is no formula / regression (i.e. $J = 1$).
M3_learner	a string specifying the regression method for $\mathbb{E}[M_3(X) Z]$ estimation.
M3_pars	a list containing hyperparameters for the M3_learner chosen.
M4_formula	a two-sided formula object for the model $\mathbb{E}[M_4(X) Z]$. Default is no formula / regression (i.e. $J = 1$)
M4_learner	a string specifying the regression method for $\mathbb{E}[M_4(X) Z]$ estimation.
M4_pars	a list containing hyperparameters for the M4_learner chosen.
M5_formula	a two-sided formula object for the model $\mathbb{E}[M_5(X) Z]$. Default is no formula / regression (i.e. $J = 1$)
M5_learner	a string specifying the regression method for $\mathbb{E}[M_5(X) Z]$ estimation.
M5_pars	a list containing hyperparameters for the M5_learner chosen.
link	link function (g). Options include identity, log, sqrt, logit, probit. De- fault is identity.
data	a data frame containing the variables for the partially linear model.
К	the number of folds used for K -fold cross-fitting. Default is 5.
S	the number of repeats to mitigate the randomness in the estimator on the sample splits used for K -fold cross-fitting. Default is 5.
max.depth	Maximum depth parameter used for ROSE random forests. Default is 5.
num.trees	Number of trees used for a single ROSE random forest. Default is 50.

roseRF_gplm

<pre>min.node.size</pre>	Minimum node size of a leaf in each tree. Default is max(10,ceiling(0.01 (K-1)/K nrow(data))).					
replace	Whether sampling for a single random tree are performed with (bootstrap) or without replacement. Default is TRUE (i.e. bootstrap).					
sample.fraction						

Proportion of data used for each random tree. Default is 0.8.

Details

The estimator of interest θ_0 solves the estimating equation

$$\sum_{i} \psi(Y_i, X_i, Z_i; \theta, \hat{\eta}(Z), \hat{w}(Z)) = 0,$$

$$\psi(Y, X, Z; \theta, \eta_0, w) := \sum_{j=1}^{J} w_j(Z) \big(M_j(X) - \mathbb{E}[M_j(X)|Z] \big) g'(\mu(X, Z; \theta, \eta_0)) \big(Y - \mu(X, Z; \theta, \eta_0) \big),$$

$$\mu(X, Z; \theta, \eta_0) := g^{-1} \big(\mathbb{E}[g(\mathbb{E}[Y|X, Z])|Z] + (X - \mathbb{E}[X|Z])\theta \big),$$

$$\eta_0 := \big(\mathbb{E}[Y|Z = \cdot], \mathbb{E}[X|Z = \cdot] \big),$$

where $M_1(X), \ldots, M_J(X)$ denotes user-chosen functions of (X) and $w(Z) = (w_1(Z), \ldots, w_J(Z))$ denotes weights estimated via ROSE random forests. The default takes J = 1 and $M_1(X) = X$; if taking $J \ge 2$ we recommend care in checking the applicability and appropriateness of any additional user-chosen regression tasks.

The parameter of interest θ_0 is estimated using a DML2 / K-fold cross-fitting framework, to allow for arbitrary (faster than $n^{1/4}$ -consistent) learners for $\hat{\eta}$ i.e. solving the estimating equation

$$\sum_{k \in [K]} \sum_{i \in I_k} \psi(Y_i, X_i, Z_i; \theta, \hat{\eta}^{(k)}(Z), \hat{w}^{(k)}(Z)) = 0,$$

where I_1, \ldots, I_K denotes a partition of the index set for the datapoints (Y_i, X_i, Z_i) , $\hat{\eta}^{(k)}$ denotes an estimator for η_0 trained on the data indexed by I_k^c , and $\hat{w}^{(k)}$ denotes a ROSE random forest (again trained on the data indexed by I_k^c).

Value

A list containing:

theta The estimator of θ_0 .

stderror Huber robust estimate of the standard error of the θ_0 -estimator.

coefficients Table of θ_0 coefficient estimator, standard error, z-value and p-value.

roseRF_pliv

Description

ROSE random forest estimator for the partially linear instrumental variable model

Usage

```
roseRF_pliv(
 y_formula,
 y_learner,
 y_pars = list(),
 x_formula,
 x_learner,
 x_pars = list(),
 IV1_formula = NA,
 IV1_learner = NA,
  IV1_pars = list(),
  IV2_formula = NA,
  IV2_learner = NA,
  IV2_pars = list(),
  IV3_formula = NA,
  IV3_learner = NA,
  IV3_pars = list(),
  IV4_formula = NA,
  IV4_learner = NA,
  IV4_pars = list(),
  IV5_formula = NA,
  IV5_learner = NA,
 IV5_pars = list(),
 data,
 K = 5,
  S = 1,
 max.depth = 10,
 num.trees = 500,
 min.node.size = max(10, ceiling(0.01 * (K - 1)/K * nrow(data))),
 replace = TRUE,
  sample.fraction = 0.8
)
```

Arguments

y_formula	a two-sided formula object describing the regression model for $\mathbb{E}[Y Z]$.
y_learner	a string specifying the regression method to fit the regression of Y on Z as given
	by y_formula (e.g. randomforest, xgboost, neuralnet, gam).

y_pars	a list containing hyperparameters for the y_learner chosen. Default is an empty list, which performs hyperparameter tuning.
x_formula	a two-sided formula object describing the regression model for $\mathbb{E}[X Z]$.
x_learner	a string specifying the regression method to fit the regression of X on Z as given by x_formula (e.g. randomforest, xgboost, neuralnet, gam).
x_pars	a list containing hyperparameters for the y_learner chosen. Default is an empty list, which performs hyperparameter tuning.
IV1_formula	a two-sided formula object for the model $\mathbb{E}[V_1(X) Z]$.
IV1_learner	a string specifying the regression method for $\mathbb{E}[V_1(X) Z]$ estimation.
IV1_pars	a list containing hyperparameters for the IV1_learner chosen.
IV2_formula	a two-sided formula object for the model $\mathbb{E}[V_2 Z]$. Default is no formula / regression (i.e. $J = 1$)
IV2_learner	a string specifying the regression method for $\mathbb{E}[V_2(X) Z]$ estimation.
IV2_pars	a list containing hyperparameters for the IV2_learner chosen.
IV3_formula	a two-sided formula object for the model $\mathbb{E}[V_3(X) Z]$. Default is no formula / regression (i.e. $J = 1$).
IV3_learner	a string specifying the regression method for $\mathbb{E}[V_3(X) Z]$ estimation.
IV3_pars	a list containing hyperparameters for the IV3_learner chosen.
IV4_formula	a two-sided formula object for the model $\mathbb{E}[V_4(X) Z]$. Default is no formula / regression (i.e. $J = 1$)
IV4_learner	a string specifying the regression method for $\mathbb{E}[V_4(X) Z]$ estimation.
IV4_pars	a list containing hyperparameters for the IV4_learner chosen.
IV5_formula	a two-sided formula object for the model $\mathbb{E}[V_5(X) Z]$. Default is no formula / regression (i.e. $J = 1$)
IV5_learner	a string specifying the regression method for $\mathbb{E}[V_5(X) Z]$ estimation.
IV5_pars	a list containing hyperparameters for the IV5_learner chosen.
data	a data frame containing the variables for the partially linear model.
К	the number of folds used for K -fold cross-fitting. Default is 5.
S	the number of repeats to mitigate the randomness in the estimator on the sample splits used for K -fold cross-fitting. Default is 5.
max.depth	Maximum depth parameter used for ROSE random forests. Default is 5.
num.trees	Number of trees used for a single ROSE random forest. Default is 50.
<pre>min.node.size</pre>	Minimum node size of a leaf in each tree. Default is max(10,ceiling(0.01 (K-1)/K nrow(data))).
replace	Whether sampling for a single random tree are performed with (bootstrap) or without replacement. Default is TRUE (i.e. bootstrap).
sample.fraction	
	Proportion of data used for each random tree. Default is 0.8.

Value

A list containing:

theta The estimator of θ_0 .

stderror Huber robust estimate of the standard error of the θ_0 -estimator.

coefficients Table of θ_0 coefficient estimator, standard error, z-value and p-value.

roseRF_plm

ROSE random forest estimator for the partially linear model

Description

Estimates the parameter of interest θ_0 in the partially linear model

$$\mathbb{E}[Y|X, Z] = X\theta_0 + f_0(Z),$$

which can be reposed in terms of the 'nuisance functions' $(\mathbb{E}[Y|X], \mathbb{E}[X|Z])$ as

$$\mathbb{E}[Y|X,Z] - \mathbb{E}[Y|Z] = (X - \mathbb{E}[X|Z])\theta_0.$$

Usage

```
roseRF_plm(
 y_formula,
 y_learner,
 y_pars = list(),
 x_formula,
 x_learner,
  x_pars = list(),
 M1_formula = x_formula,
 M1_learner = x_learner,
 M1_pars = x_pars,
 M2_formula = NA,
 M2\_learner = NA,
 M2_pars = list(),
 M3_formula = NA,
 M3_learner = NA,
 M3_pars = list(),
 M4_formula = NA,
 M4_learner = NA,
 M4_pars = list(),
 M5_formula = NA,
 M5_learner = NA,
 M5_pars = list(),
 data,
 K = 5,
  S = 1,
```

roseRF_plm

```
max.depth = 10,
num.trees = 500,
min.node.size = max(10, ceiling(0.01 * (K - 1)/K * nrow(data))),
replace = TRUE,
sample.fraction = 0.8
)
```

Arguments

y_formula	a two-sided formula object describing the model for $\mathbb{E}[Y Z]$.
y_learner	a string specifying the regression method to fit the regression of Y on Z as given by y_formula (e.g. randomforest, xgboost, neuralnet, gam).
y_pars	a list containing hyperparameters for the y_learner chosen. Default is an empty list, which performs hyperparameter tuning.
x_formula	a two-sided formula object describing the model for $\mathbb{E}[X Z]$.
x_learner	a string specifying the regression method to fit the regression of X on Z as given by x_formula (e.g. randomforest, xgboost, neuralnet, gam).
x_pars	a list containing hyperparameters for the y_learner chosen. Default is an empty list, which performs hyperparameter tuning.
M1_formula	a two-sided formula object for the model $\mathbb{E}[M_1(X) Z]$. Default is $M_1(X) = X$.
M1_learner	a string specifying the regression method for $\mathbb{E}[M_1(X) Z]$ estimation.
M1_pars	a list containing hyperparameters for the M1_learner chosen.
M2_formula	a two-sided formula object for the model $\mathbb{E}[M_2(X) Z]$. Default is no formula / regression (i.e. $J = 1$)
M2_learner	a string specifying the regression method for $\mathbb{E}[M_2(X) Z]$ estimation.
M2_pars	a list containing hyperparameters for the M2_learner chosen.
M3_formula	a two-sided formula object for the model $\mathbb{E}[M_3(X) Z]$. Default is no formula / regression (i.e. $J = 1$).
M3_learner	a string specifying the regression method for $\mathbb{E}[M_3(X) Z]$ estimation.
M3_pars	a list containing hyperparameters for the M3_learner chosen.
M4_formula	a two-sided formula object for the model $\mathbb{E}[M_4(X) Z]$. Default is no formula / regression (i.e. $J = 1$)
M4_learner	a string specifying the regression method for $\mathbb{E}[M_4(X) Z]$ estimation.
M4_pars	a list containing hyperparameters for the M4_learner chosen.
M5_formula	a two-sided formula object for the model $\mathbb{E}[M_5(X) Z]$. Default is no formula / regression (i.e. $J = 1$)
M5_learner	a string specifying the regression method for $\mathbb{E}[M_5(X) Z]$ estimation.
M5_pars	a list containing hyperparameters for the M5_learner chosen.
data	a data frame containing the variables for the partially linear model.
К	the number of folds used for K -fold cross-fitting. Default is 5.
S	the number of repeats to mitigate the randomness in the estimator on the sample splits used for K -fold cross-fitting. Default is 5.

max.depth	Maximum depth parameter used for ROSE random forests. Default is 5.				
num.trees	Number of trees used for a single ROSE random forest. Default is 50.				
<pre>min.node.size</pre>	Minimum node size of a leaf in each tree. Default is max(10,ceiling(0.01 (K-1)/K nrow(data))).				
replace	Whether sampling for a single random tree are performed with (bootstrap) or without replacement. Default is TRUE (i.e. bootstrap).				
sample.fraction					

Proportion of data used for each random tree. Default is 0.8.

Details

The estimator of interest θ_0 solves the estimating equation

$$\sum_{i} \psi(Y_i, X_i, Z_i; \theta, \hat{\eta}(Z), \hat{w}(Z)) = 0,$$

$$\psi(Y, X, Z; \theta, \eta_0, w) := \sum_{j=1}^J w_j(Z) \left(M_j(X) - \mathbb{E}[M_j(X)|Z] \right) \left(\left(Y - \mathbb{E}[Y|Z] \right) - \left(X - \mathbb{E}[X|Z] \right) \theta \right),$$
$$\eta_0 := \left(\mathbb{E}[Y|Z = \cdot], \mathbb{E}[X|Z = \cdot] \right),$$

where $M_1(X), \ldots, M_J(X)$ denotes user-chosen functions of (X) and $w(Z) = (w_1(Z), \ldots, w_J(Z))$ denotes weights estimated via ROSE random forests. The default takes J = 1 and $M_1(X) = X$; if taking $J \ge 2$ we recommend care in checking the applicability and appropriateness of any additional user-chosen regression tasks.

The parameter of interest θ_0 is estimated using a DML2 / K-fold cross-fitting framework, to allow for arbitrary (faster than $n^{1/4}$ -consistent) learners for $\hat{\eta}$ i.e. solving the estimating equation

$$\sum_{k \in [K]} \sum_{i \in I_k} \psi(Y_i, X_i, Z_i; \theta, \hat{\eta}^{(k)}(Z), \hat{w}^{(k)}(Z)) = 0,$$

where I_1, \ldots, I_K denotes a partition of the index set for the datapoints (Y_i, X_i, Z_i) , $\hat{\eta}^{(k)}$ denotes an estimator for η_0 trained on the data indexed by I_k^c , and $\hat{w}^{(k)}$ denotes a ROSE random forest (again trained on the data indexed by I_k^c).

Value

A list containing:

theta The estimator of θ_0 .

stderror Huber robust estimate of the standard error of the θ_0 -estimator.

coefficients Table of θ_0 coefficient estimator, standard error, z-value and p-value.

summary.roseforest Summary for a rose random forest fitted object

Description

Prints a roseRF object fitted by the functions roseRF.... in roseRF.

Usage

```
## S3 method for class 'roseforest'
summary(object, ...)
```

Arguments

object	a fitted roseRF object fitted by roseRF
	additional arguments

Value

Prints summary output for roseRF object

unweighted_gplm	Unweighted (baseline) estimator for the generalised partially linear
	model

Description

Estimates the parameter of interest θ_0 in the generalised partially linear regression model

$$g(\mathbb{E}[Y|X,Z]) = X\theta_0 + f_0(Z),$$

as in roseRF_gplm but without any weights i.e. J = 1, $M_1(X) = X$ and $w_1 \equiv 1$.

Usage

```
unweighted_gplm(
 y_on_xz_formula,
 y_on_xz_learner,
 y_on_xz_pars = list(),
 Gy_on_z_formula,
 Gy_on_z_learner,
 Gy_on_z_pars = list(),
 x_formula,
 x_learner,
 x_pars = list(),
 link = "identity",
```

	da	ata	a,
	Κ	=	5,
	S	=	1
)			

Arguments

a two-sided formula object describing the regression model for $\mathbb{E}[Y X, Z]$ (regressing Y on (X, Z)).		
y_on_xz_learner		
a string specifying the regression method to fit the regression as given by y_on_xz_formula (e.g. randomforest, xgboost, neuralnet, gam).		
a list containing hyperparameters for the y_on_xz_learner chosen. Default is an empty list, which performs hyperparameter tuning.		
Gy_on_z_formula		
a two-sided formula object describing the regression model for $\mathbb{E}[g(\mathbb{E}[Y X, Z]) Z]$ (regressing $g(\hat{E}[Y X, Z])$ on Z).		
Gy_on_z_learner		
a string specifying the regression method to fit the regression as given by Gy_on_z_formula (e.g. randomforest, xgboost, neuralnet, gam).		
a list containing hyperparameters for the Gy_on_z_learner chosen. Default is an empty list, which performs hyperparameter tuning.		
a two-sided formula object describing the regression model for $\mathbb{E}[X Z]$.		
a string specifying the regression method to fit the regression of X on Z as given by x_formula (e.g. randomforest, xgboost, neuralnet, gam).		
a list containing hyperparameters for the x_learner chosen. Default is an empty list, which performs hyperparameter tuning.		
link function (g). Options include identity, log, sqrt, logit, probit. De- fault is identity.		
a data frame containing the variables for the partially linear model.		
the number of folds used for K -fold cross-fitting. Default is 5.		
the number of repeats to mitigate the randomness in the estimator on the sample splits used for K -fold cross-fitting. Default is 5.		

Value

A list containing:

theta The estimator of θ_0 .

stderror Huber robust estimate of the standard error of the $\theta_0\text{-estimator.}$

coefficients Table of θ_0 coefficient estimator, standard error, z-value and p-value.

12

unweighted_plm

Description

Estimates the parameter of interest θ_0 in the partially linear regression model

 $\mathbb{E}[Y|X, Z] = X\theta_0 + f_0(Z),$

as in roseRF_plm but without any weights i.e. J = 1, $M_1(X) = X$ and $w_1 \equiv 1$.

Usage

```
unweighted_plm(
  y_formula,
  y_learner,
  y_pars = list(),
  x_formula,
  x_learner,
  x_pars = list(),
  data,
  K = 5,
  S = 1
)
```

Arguments

y_formula	a two-sided formula object describing the regression model for $\mathbb{E}[Y Z]$.
y_learner	a string specifying the regression method to fit the regression of Y on Z as given by y_formula (e.g. randomforest, xgboost, neuralnet, gam).
y_pars	a list containing hyperparameters for the y_learner chosen. Default is an empty list, which performs hyperparameter tuning.
x_formula	a two-sided formula object describing the regression model for $\mathbb{E}[X Z]$.
x_learner	a string specifying the regression method to fit the regression of X on Z as given by x_formula (e.g. randomforest, xgboost, neuralnet, gam).
x_pars	a list containing hyperparameters for the y_learner chosen. Default is an empty list, which performs hyperparameter tuning.
data	a data frame containing the variables for the partially linear model.
К	the number of folds used for K -fold cross-fitting. Default is 5.
S	the number of repeats to mitigate the randomness in the estimator on the sample splits used for K -fold cross-fitting. Default is 5.

Value

A list containing:

theta The estimator of θ_0 .

stderror Huber robust estimate of the standard error of the θ_0 -estimator.

coefficients Table of θ_0 coefficient estimator, standard error, z-value and p-value.

Index

 ${\tt print.roseforest, 2}$

roseRF_gplm, 2
roseRF_pliv, 6
roseRF_plm, 8

summary.roseforest, 11

unweighted_gplm, 11 unweighted_plm, 13